


Parefeux sous OMV



The screenshot shows the OpenMediaVault web interface for firewall configuration. The 'Pare-feu' tab is active, displaying a list of IPv4 rules. The table below represents the data shown in the interface.

| Direction | Action | Famille | Source | Port | Destina... | Port | Proto... | Options supplémentaires | Commentaire |
|-----------|--------|---------|----------------|------|------------|------|----------|--|---|
| INPUT | ACCEPT | IPv4 | - | - | - | - | Tous | -i lo | Autoriser le trafic local |
| OUTPUT | ACCEPT | IPv4 | - | - | - | - | Tous | -o lo | Autoriser le trafic local |
| INPUT | ACCEPT | IPv4 | - | - | - | - | Tous | -m conntrack --ctstate ESTABLISHED,RELATED | Conserver les connexions déjà établies |
| INPUT | ACCEPT | IPv4 | 192.168.1.2 | - | - | - | Tous | | Accès total à partir d'un poste particulier |
| INPUT | ACCEPT | IPv4 | 192.168.1.0/24 | - | - | - | ICMP | | PING en local |
| INPUT | ACCEPT | IPv4 | 192.168.1.0/24 | - | - | 5000 | TCP | | Accès à OpenMediaVault |
| INPUT | ACCEPT | IPv4 | - | - | - | 22 | TCP | | Autoriser SSH |
| INPUT | ACCEPT | IPv4 | - | - | - | 80 | TCP | | Autoriser HTTP |
| INPUT | ACCEPT | IPv4 | - | - | - | 443 | TCP | | Autoriser HTTPS |
| INPUT | ACCEPT | IPv4 | - | - | - | 137 | UDP | | Samba : NetBIOS Name Service |
| INPUT | ACCEPT | IPv4 | - | - | - | 138 | UDP | | Samba : NetBIOS Datagram Service |
| INPUT | ACCEPT | IPv4 | - | - | - | 139 | TCP | | Samba : NetBIOS Session Service |
| INPUT | ACCEPT | IPv4 | - | - | - | 445 | TCP | | Samba : SMB/CIFS Service |
| INPUT | ACCEPT | IPv4 | - | - | - | 53 | UDP | | DNS |
| INPUT | ACCEPT | IPv4 | - | - | - | 53 | TCP | | DNS |
| INPUT | DROP | IPv4 | - | - | - | - | Tous | | Interdire tout ce qui n'est pas autorisé |

From: <https://chanterie37.fr/fablab37110/> - Castel'Lab le Fablab MJC de Château-Renault

Permanent link: <https://chanterie37.fr/fablab37110/doku.php?id=start:raspberry:nas:firewall&rev=1736575800>

Last update: 2025/01/11 07:10

